


CEDA USER'S MANUAL(U) MITRE CORP BEDFORD MA  
J R CALABRO ET AL. JAN 83 MTR-8658 ESD-TR-82-418  
F19628-82-C-0001

**UNCLASSIFIED**

F/G 9/2

NL



MICROCOPY RESOLUTION TEST CHART  
NATIONAL BUREAU OF STANDARDS-1963-A

ESD-TR-82-418

MTR-8658

AD A125183

**CEDA USER'S MANUAL**

By  
**J. R. CALABRO**  
**M. M. POZZO**

**JANUARY 1983**

Prepared for  
**DEPUTY FOR DEVELOPMENT PLANS**  
**ELECTRONIC SYSTEMS DIVISION**  
**AIR FORCE SYSTEMS COMMAND**  
**UNITED STATES AIR FORCE**  
**Hanscom Air Force Base, Massachusetts**



DTIC  
SERIAL  
E

DTIC FILE COPY

Approved for public release;  
distribution unlimited.

Project No. 496B  
Prepared by  
**THE MITRE CORPORATION**  
Bedford, Massachusetts  
Contract No. F19628-82-C-0001

88 03 02 025

When U.S. Government drawings, specifications, or other data are used for any purpose other than a definitely related government procurement operation, the government thereby incurs no responsibility nor any obligation whatsoever; and the fact that the government may have formulated, furnished, or in any way supplied the said drawings, specifications, or other data is not to be regarded by implication or otherwise, as in any manner licensing the holder or any other person or corporation, or conveying any rights or permission to manufacture, use, or sell any patented invention that may in any way be related thereto.

Do not return this copy. Retain or destroy.

### REVIEW AND APPROVAL

This technical report has been reviewed and is approved for publication.

FOR THE COMMANDER



EDWIN W. KNOX, 2Lt USAF  
Project Officer, C2 CONCAP



CHARLES J. LaBLONDE, Lt Col, USAF  
Acting Director  
Advanced Concepts and Technology  
Deputy for Development Plans

UNCLASSIFIED

SECURITY CLASSIFICATION OF THIS PAGE (When Data Entered)

REPORT DOCUMENTATION PAGE		READ INSTRUCTIONS BEFORE COMPLETING FORM
1. REPORT NUMBER ESD-TR-82-418	2. GOVT ACCESSION NO. AD-A123183	3. RECIPIENT'S CATALOG NUMBER
4. TITLE (and Subtitle)  CEDA USER'S MANUAL		5. TYPE OF REPORT & PERIOD COVERED
		6. PERFORMING ORG. REPORT NUMBER MTR-8658
7. AUTHOR(s)  J. R. CALABRO, M. M. POZZO		8. CONTRACT OR GRANT NUMBER(s)  F19628-82-C-0001
9. PERFORMING ORGANIZATION NAME AND ADDRESS The MITRE Corporation Burlington Road Bedford, MA 01730		10. PROGRAM ELEMENT, PROJECT, TASK AREA & WORK UNIT NUMBERS  Project No. 496B
11. CONTROLLING OFFICE NAME AND ADDRESS Deputy for Development Plans Electronic Systems Division, AFSC Hanscom AFB, MA 01731		12. REPORT DATE JANUARY 1983
14. MONITORING AGENCY NAME & ADDRESS (if different from Controlling Office)		13. NUMBER OF PAGES 124
		15. SECURITY CLASS. (of this report)  UNCLASSIFIED
15a. DECLASSIFICATION/DOWNGRADING SCHEDULE		
16. DISTRIBUTION STATEMENT (of this Report)  Approved for public release; distribution unlimited.		
17. DISTRIBUTION STATEMENT (of the abstract entered in Block 20, if different from Report)		
18. SUPPLEMENTARY NOTES		
19. KEY WORDS (Continue on reverse side if necessary and identify by block number) AUTOMATED TACTICAL AIDS DECISION AIDS HUMAN FACTORS MISSION PLANNING WEAPONNEERING		
20. ABSTRACT (Continue on reverse side if necessary and identify by block number)  The Air Force is involved in research in the area of human performance and training; specifically, the interaction of human factors with the effectiveness of C <sup>2</sup> systems. A software system which is a Capability for Evaluating Decision Aids (CEDA) was developed using the ESD CONCAP capability at MITRE. CEDA will be used by the Human Resources Laboratory for testing human performance on a tactical operations problem as the amount of information and form of presentation are varied.  This document contains the specific instructions for operating CEDA.		

UNCLASSIFIED

## ACKNOWLEDGMENTS

The authors wish to acknowledge the technical support of Sarah Chayes, Judy Clapp, Andy Feit, R. C. Hanckel, Frank Perron, and R. E. Wagner, who all assisted in the software development and in putting this manual together. Thanks also to Barbara Richard for her secretarial and editing support.

This report has been prepared by The MITRE Corporation under Project 496B. The contract is sponsored by the Electronic Systems Division, Air Force Systems Command, Hanscom Air Force Base, Massachusetts.

Accession For	
NTIS GRA&I	<input checked="" type="checkbox"/>
DTIC TAB	<input type="checkbox"/>
Unannounced	<input type="checkbox"/>
Justification	
By	
Distribution /	
Availability Codes	
Dist. Statement /	
Dist. Statement	
A	



## TABLE OF CONTENTS

<u>Section</u>		<u>Page</u>
	LIST OF ILLUSTRATIONS	5
1.0	INTRODUCTION	9
1.1	CEDA PROJECT 4960	9
1.2	GENERAL	9
1.3	CONTENTS	10
2.0	CEDA OVERVIEW	11
2.1	INTRODUCTION	11
2.2	SOFTWARE DEVELOPMENT OVERVIEW	11
2.2.1	Application	11
2.2.2	System Description	11
2.2.3	Data Base	12
2.3	CEDA CAPABILITIES	13
2.3.1	User Functions	13
2.3.2	Tabular Displays	14
2.3.3	Graphics Displays	17
2.3.4	Decision Aids	17
2.3.5	Data Collection	20
2.3.6	Peripheral Devices	21

## TABLE OF CONTENTS (Concluded)

<u>Section</u>	<u>Page</u>
3.0 OPERATING INSTRUCTIONS	22
3.1 INTRODUCTION	22
3.2 SESSION INITIALIZATION	22
3.3 LOGIN SESSION STARTUP	26
3.4 FUNCTION KEYS	26
4.0 SAMPLE CEDA SESSION	38
4.1 INTRODUCTION	38
4.2 THE TACTICAL SCENARIO	38
4.3 THE CEDA SESSION	39
APPENDIX A MENUS	42
APPENDIX B TABLES	51
APPENDIX C FUNCTION FLOW	98
APPENDIX D SYSTEM EVENT CODES	111
APPENDIX E USER RESPONSE CODES	114
APPENDIX F SAMPLE SESSION DATA	116
GLOSSARY	118
DISTRIBUTION LIST	121



## LIST OF ILLUSTRATIONS

<u>Figure</u>	<u>Page</u>
2-1 VT100 Keyboard	15
2-2 Tektronix 4027 Keyboard	18
2-3 Foreground Symbols	19
3-1 Default Function Key Layout	25
A-1 Graphic Options Menu (MN01)	43
A-2 Data Base Search Menu (MN02)	44
A-3 Allocation Menu (MN07)	45
A-4 Interactive Allocation/Weapon Decision (MN08)	46
A-5 Interactive Allocation/Airbase Decision (MN09)	47
A-6 Interactive Allocation/Mission Decision (MN9B)	48
A-7 Planned Missions (MN10)	49
A-8 Airbase Prioritization (MN11)	50
B-1 Target Description (TB01)	52
B-2 Identified Target Summary (TB03)	53
B-3a Friendly Airbase Description (TB04)	54
B-3b Friendly Airbase Description (Aircraft Possessed)	55
B-3c Friendly Airbase Description (Alert Aircraft)	56
B-3d Friendly Airbase Description (Ordnance)	57
B-3e Friendly Airbase Description (Runways)	58

# LIST OF ILLUSTRATIONS (Continued)

<u>Figure</u>	<u>Page</u>
B-3f Friendly Airbase Description (POL)	59
B-4a Friendly Airbase Summary (TB05) (Page 1)	60
B-4b Friendly Airbase Summary (TB05) (Page 2)	61
B-4c Friendly Airbase Summary (TB05) (Page 3)	62
B-4d Friendly Airbase Summary (TB05) (Page 4)	63
B-4e Friendly Airbase Summary (TB05) (Page 5)	64
B-4f Friendly Airbase Summary (TB05) (Page 6)	65
B-4g Friendly Airbase Summary (TB05) (Page 7)	66
B-4h Friendly Airbase Summary (TB05) (Page 8)	67
B-4i Friendly Airbase Summary (TB05) (Page 9)	68
B-4j Friendly Airbase Summary (TB05) (Page 10)	69
B-4k Friendly Airbase Summary (TB05) (Page 11)	70
B-4l Friendly Airbase Summary (TB05) (Page 12)	71
B-5 Mission Schedule (TB06)	72
B-6a Enemy Order of Battle-Ground (TB07) (Page 1)	73
B-6b Enemy Order of Battle-Ground (TB07) (Page 2)	74
B-6c Enemy Order of Battle-Ground (TB07) (Page 3)	75
B-7 Enemy Order of Battle-Air (TB08)	76
B-8 Enemy Order of Battle-Electronic (TB09)	77
B-9a Enemy Order of Battle-SAM/AAA (TB10) (Page 1)	78
B-9b Enemy Order of Battle-SAM/AAA (TB10) (Page 2)	79

# LIST OF ILLUSTRATIONS (Continued)

<u>Figure</u>	<u>Page</u>
B-9c Enemy Order of Battle-SAM/AAA (TB10) (Page 3)	80
B-10 Fighter Schedule (TB11)	81
B-11 Alert Aircraft (TB12)	82
B-12 Command and Control Centers (TB13)	83
B-13 Generic Target Types (TB14)	84
B-14a Ordnance Load Codes (TB15) (Page 1)	85
B-14b Ordnance Load Codes (TB15) (Page 2)	86
B-14c Ordnance Load Codes (TB15) (Page 3)	87
B-14d Ordnance Load Codes (TB15) (Page 4)	88
B-15a Aircraft Characteristics (TB16) (Page 1)	89
B-15b Aircraft Characteristics (TB16) (Page 2)	90
B-15c Aircraft Characteristics (TB16) (Page 3)	91
B-15d Aircraft Characteristics (TB16) (Page 4)	92
B-15e Aircraft Characteristics (TB16) (Page 5)	93
B-16 Identify Line-Targets (TB17)	94
B-17 Identify Line-Friendly Airbases (TB18)	95
B-18 Air Tasking Order (TB20)	96
B-19 Continue Session (TB21)	97
C-1 Function Key #1 - Graphic Options Menu	99
C-2 Function Key #2 - Data Base Search Menu	100
C-3 Function Key #3 - Identify	101

## LIST OF ILLUSTRATIONS (Concluded)

<u>Figure</u>		<u>Page</u>
C-4	Function Key #4 - Full Page Descriptor	102
C-5	Function Key #5 - Grid	103
C-6	Function Key #6 - Zoom 1	104
C-7	Function Key #7 - Zoom 2	105
C-8	Function Key #8 - Zoom 3	106
C-9	Function Key #9 - Airbase Prioritization Menu	107
C-10	Function Key #10 - Interactive Allocation Menu	108
C-11	Function Key #11 - Air Tasking Order	109
C-12	Function Key #12 - Start/Stop	110

## SECTION 1

### INTRODUCTION

#### 1.1 CEDA PROJECT 4960

The Human Resources Laboratory (HRL) at Wright Patterson Air Force Base is conducting in-house research on how human factors affect operation of C<sup>2</sup> systems. This work is being done to complement a larger effort by the Air Force in the area of human performance and training. MITRE has been tasked, under Project 4960, to develop a Capability for Evaluating Decision Aids (CEDA) which will provide an experimental capability to analyze user performance as a result of automated tactical decision aids. This software capability can be used to evaluate new concepts for command and control systems and to refine the human interface to automated decision aids.

To develop such a system, the decision aids and overall capabilities of the Tactical Operations Planner (TOP) Phase 2 system were used as a model. Stimulus control features, data recording for protocol analysis, collection of user response times, and the "pulsing" of peripheral devices for additional dependent measurements are incorporated into CEDA to enable rather detailed C<sup>2</sup> system evaluations to be made.

#### 1.2 GENERAL

As previously stated, CEDA will assist researchers in determining how the availability and design of automated decision aids affect C<sup>2</sup> decision making. It was designed to be flexible, permitting expansion and modification in both the number and form of decision aids presented and in the data base used to drive the software.

The CEDA software was developed to provide an experimental capability for analysis of user performance as a result of automated presentation of information. CEDA is controlled by user commands. The initial system supports a two-terminal configuration called a work station. Each station consists of a graphics terminal and a video terminal.

The graphics terminal displays geographic maps from the data base and provides a means by which the user can alter the display to get the desired view of the map.

The video terminal accepts user commands through its keyboard and displays tabular information from the data base. It also displays tabular menus which either accept user commands for more specific types of tabular

information, allows the user to manipulate the information in the data base or permits the user to alter the amount and type of information displayed on the geographic map located on the graphic display.

In addition, data recording can be enabled for a session. The information recorded (user commands, user responses and user response times, system responses) can be used to analyze the performance of the user.

Peripheral devices which measure brain waves or eye movement may also be driven by CEDA for additional dependent measurement of user actions. As with the data recording, this feature need not be invoked to permit CEDA to function properly. Details of these two capabilities are further described in Section 3. Other experimental control features have been added to CEDA. These features are intended to permit precise recording of user actions and provide a framework for comparing session results. These are also discussed in more detail in Section 3.

### 1.3 CONTENTS

As a user's manual, this document contains a brief overview of the system software, data base, and CEDA capabilities (Section 2, "CEDA Overview"), detailed operating instructions (Section 3, "Operating Instructions") and a "typical session" example (Section 4, "Sample CEDA Session"). Appendices A and B contain the Menus and Tables respectively. A functional flow diagram for each user aid available is presented in Appendix C. System Event and User Response Codes are in Appendices D and E, and Sample Session Data is in Appendix F. A Glossary has been included at the end of the manual for terms, acronyms and abbreviations used throughout this manual which may not be well-known to the user.

For a general description of the software design and data base currently used for CEDA, refer to the "CEDA High-Level Software System Design" document<sup>1</sup>.

---

<sup>1</sup>J. Calabro, M. Pozzo, "CEDA High-Level Software System Design," ESD-TR-82-419, Electronic Systems Division, AFSC, Hanscom AFB, MA 01731. (In process)

## SECTION 2

### CEDA OVERVIEW

#### 2.1 INTRODUCTION

This section presents a brief discussion of the software and data base development and an overview of CEDA functions, tabular features, graphics and decision aids. Section 3, "Operating Instructions", provides more detailed instructions for operating CEDA. As stated, a more thorough discussion of the CEDA software design itself and data base can be found in the "CEDA High-Level Software System Design" document referred to in Section 1.

#### 2.2 SOFTWARE DEVELOPMENT OVERVIEW

##### 2.2.1 Application

The decision aids and data base available in the initial CEDA system were modeled after the TOP Phase 2 system. However, since the purpose of CEDA is not tactical planning, per se, the system was redesigned and expanded to encompass the human factors features discussed in Section 1. The main purposes of this system are twofold: to create a system which allows a variety of tactical command and control concepts to be tested and evaluated, to gather data on how automated aids affect tactical operations.

##### 2.2.2 System Description

The system designed consists of six functional modules and an overall system executive. The main purpose for doing this is to allow ease of maintenance and the addition of future enhancements. This structure affords a great deal of flexibility in that each module may be expanded or altered completely and installed in place of the old one with no effect on the other modules. In addition, this provides a more efficient use of memory since a module need only be brought into memory as it is needed. A brief description of the modules and system executive, which are coded entirely in Fortran IV-Plus, follows.

System Executive - initiates and concludes the session for each user.

User Function Module - controls the handling of a function key invocation and brings the necessary module(s) into memory.

Menu Module - displays all menus and processes the user input to the menu.

**Table Module - displays all tables (no user input).**

**Data Base Module - handles all requests from the other modules to access information from any of the disk-resident data base files.**

**Graphics Module - performs all operations to display or alter the display on the graphics terminal.**

**Decision Aid Module - performs weaponeering for weapon choice allocation and airbase choice allocation. Also creates the resulting mission and handles the Air Tasking Order Function.**

It should be noted that each module consists of one or more packages, again for ease of modification. For example, the Data Base Module contains a translate package for interpreting the request (known as a DML - data manipulation language - statement) and an I/O package for accessing the files. In this way, a different request language can be used and only the translate package need be replaced, or a new set of files may be supplied and only the I/O package need be replaced.

### **2.2.3 Data Base**

The CEDA (tactical and weaponeering) data base was taken from that used in the TOP system. The tactical data base was originally developed by Air Force Intelligence personnel and weaponeering information was based on results generated by the Automatic Weaponeering Optimization Program (AWOP).

Access to the Data Base is not through direct user interaction; therefore, details of this module are not included in this document. Information can be found, however, in the "CEDA High-Level Software System Design" document as follows:

- o Section 3.4 - Data Base Executive Module description including details of the two packages contained in this module as well as supporting routines.
- o Section 4.2 - Data Base Files description, includes characteristics of each file as well as creation method and a general description.
- o Appendix E - Data Dictionary and Record Layouts, gives the actual record format for each disk-resident file that supports CEDA.



## **2.3 CEDA CAPABILITIES**

### **2.3.1 User Functions**

Listed below are the currently available user functions in key order (see Section 3, "Operating Instructions") and a brief description of what they do.

#### **1. Graphic Options**

Allows the user to change the appearance of the graphic display, either by changing the color of elements, or by removing or adding elements to the display.

#### **2. Data Base Search**

Allows the user to obtain tabular data such as ordnance load codes, identified targets, friendly airbases, planned missions, etc.

#### **3. Identify**

Gives brief information on an element (target or airbase) indicated by the cursor on the graphics screen. Note: Only identified targets are added to the Identified List.

#### **4. Full Page Descriptor**

Gives more complete information on an object (target or airbase) which was specified by the user through cursor input, without adding it to the Identified List.

#### **5. Grid**

Superimposes a grid on the geographic map to distinguish individual areas for zoom.

#### **6. Zoom 1**

Smallest graphics magnification: displays map at magnification used as session start up (all four quadrants).

#### **7. Zoom 2**

Zooms a quarter of the map to full screen size

#### 8. Zoom 3

Zooms a sixteenth of the map to full screen size.

#### 9. Airbase Prioritization

Allows the user to set the rules whereby the computer orders and displays the bases capable of supporting a given mission.

#### 10. Interactive Allocator

The actual decision phase of CEDA: provides computer-assessed information during the mission planning process using the information collected from the other CEDA functions (visual aids as well as tabular data). The result of this process is the allocation of aircraft/weapon combinations against specific targets. A maximum of 16 planned missions is possible at one time.

#### 11. Air Tasking Order

Generates an Air Tasking Order, visual as well as hardcopy, from missions currently confirmed.

#### 12. Start/Stop

Initiates and concludes session.

#### 2.3.2 Tabular Displays

As previously stated, CEDA includes two separate visual components: graphics display containing geographic maps with symbols marking the location of targets and airbases and other foreground information to define the current tactical scenario, and tabular display containing tabular information arrayed either in static tables or menus requesting user input.

The current CEDA system uses a DEC VT100 video terminal, which consists of a monitor and detachable keyboard, to present the tabular displays. There are twenty four lines for display on the VT100 terminal. The first twenty-three are used for presentation of tabular displays (called the workspace). Only the last line, the monitor, is reserved for machine error or CEDA generated error messages. The keyboard consists of the standard typewriter keys, special function keys, and a keypad. Figure 2-1 shows the VT100 keyboard layout.




Figure 2-1. VT100 Keyboard

The tabular displays themselves are divided into two categories: menus and tables. Menus accept and act on user input. They offer a series of options from among which the user indicates his choice by typing entries in the appropriate blanks. Through the medium of menus, a user may effect such operations as changing the appearance of the graphics display, requesting data, setting criteria to be used in the allocation process, and actually allocating airbases and weapons against targets. Most menus are accessed directly from function keys. In addition, while the user is within a menu, he may at any time before entering his final response, cancel the menu entirely and exit from the current function.

Tables on the other hand, are to present information only, like the Identified Targets Summary, which gives the identification numbers, BE numbers, names, priorities, types, and other characteristics of all the identified targets. Many tables are accessed from menus, especially the Data Base Search Menu, but some can be obtained directly from function keys. For example, the Identify and Full Page Functions will directly produce tables.

There are twenty-eight menus and tables in the current version of CEDA listed below:

#### Menus

Graphic Options Menu  
Data Base Search Menu  
Allocation Menu  
Interactive Allocation-Weapons  
Decision  
Interactive Allocation-Airbase  
Decision  
Interactive Allocation-Mission  
Decision  
Planned Missions  
Airbase Prioritization Menu

#### Tables

Target Description  
Identified Target Summary  
Friendly Airbase Description  
Friendly Airbase Summary  
Mission Schedule  
Enemy Order of Battle-Ground  
Enemy Order of Battle-Air  
Enemy Order of Battle-Elect  
Enemy Order of Battle-SAM/AAA  
Fighter Schedule  
Alert Aircraft  
Command and Control Centers  
Target Types  
Ordnance Load Codes  
Aircraft Characteristics  
Identify-Targets  
Identify-Friendly Airbases  
Air Tasking Order  
Continue Session

For the actual format of menus and tables, see Appendices A and B.

### 2.3.3 Graphics Displays

The CEDA geographically based visual aids are displayed either on a Tektronix 4027 color graphics terminal or a Ramtek 9400 graphics monitor. The Tektronix 4027 color graphics terminal consists of a graphics display monitor and detachable keyboard. The keyboard has the standard typewriter keys, function keys, and a cursor/numeric pad. The graphics cursor is invoked through the use of the cursor/numeric pad. Figure 2-2 shows the Tektronix 4027 keyboard layout. The Ramtek 9400 does not include a keyboard. Cursor control is invoked through the use of a track ball.


The background for all of the displays is a map and nautical miles scale for the tactical operations area. At the beginning of a user session, this map (showing political boundaries, as well as cities of population above 1,000,000) will appear on the graphics screen. On the map are colored symbols marking the location of the various elements of foreground information. Each kind of element is represented by a unique symbol. See Figure 2-3 for a list of symbols representing the foreground information.

A user may modify the geographic display in a number of ways:

1. When a user identifies any target, using the Identify Function, a white identification number appears to its right on the graphics screen.
2. The Zoom 2 Function zooms a user-selected area which represents a quarter of the map to full screen size. At the invocation of Zoom 2, cities with population over 500,000 will appear on the map.
3. The Zoom 3 Function zooms a user-selected area which represents a sixteenth of the map to full screen size. Now all cities with population above 250,000 will appear.
4. The Zoom 1 Function returns the map to the scale it had at the beginning of the session.
5. The Graphic Options Menu allows the user to change the color of sets of symbols or delete (or add) symbols from the map.

### 2.3.4 Decision Aids

Several decision aids are provided to help the user in the mission planning phase. Once the user has determined which targets to allocate against (using the other features of CEDA) the weapons choice decision aid comes into play.



2087-1


Figure 2-2. Tektronix 4027 Keyboard

### Friendly Foreground Information

Friendly Airbases: 

Command and Control Centers: 


### Enemy Order of Battle and Nominated Targets

Enemy Airbase: 

SAM Site: 

AAA: 

Bridge: 

EW/GCI: 

POL: 

Miscellaneous Fixed Target: 

Miscellaneous Mobile Target: 

Figure 2-3. Foreground Symbols

Given the specific target and selection criteria for aircraft, ordnance and airbase, weaponeering is performed by the weapons choice decision aid which supplies the user with up to six weapon/aircraft combinations for inspection and selection.

Once the user has made a weapon/aircraft choice, the airbase choice decision aid takes over. This aid provides the user with up to three possible bases that can supply the weapon/aircraft combination requested. The user is prompted however, if no weapon or base can supply the mission. In this case or in the case that the user is not satisfied with the choices, the user has the option to choose a different weapon/aircraft combination.

When an airbase has been selected, the make-mission decision aid builds the mission and presents it to the user. At this point, the user can accept the mission or go back to any of the other decision aids. Rejection of a target can occur at any point.

The remaining decision aid, Air Tasking Order, prints all confirmed missions on the line printer and the VT100 terminal and changes their state within the data base to fragged.

#### 2.3.5 Data Collection

One of the key experimental features of CEDA is the data collection and recording capability, which will permit an analyst to correlate system stimuli with user response. Throughout each user session, data is collected on the following:

- . system events - system stimuli (e.g., graphics display, menu)
- . user responses - action taken by user after system event
- . user response times - time between system event and user response
- . menu entries - user entries within each menu

This data is recorded on a disk file under the user's last name (up to eight characters). The first record in the user's file is the login record and it has the following form:

<u>Col.</u>	<u>Data</u>
1-5	'LOGIN'
7-14	user's name
16-19	user's rank
31-36	session date (mmddyy)
46-53	session time (hh:mm:ss)

All remaining records are either system event records or menu entry records. System event refers to any computer driven stimulus presented



to the user (e.g., graphics display, menu display). Each system event is recorded as a system event record. If the event is the display of menu, subsequent records (menu entries) are added to identify user entries made in the menu.

The format for each system event record is as follows:

<u>Col.</u>	<u>Data</u>
1-5	'EVENT'
7-10	system event code
12-21	user response time
23-26	user response code
28-37	if menu, time to complete menu entries otherwise, 0.0 is recorded

As stated above, if the system event is a menu, a list of user entries is also recorded where lower case letters represent user inputs and upper case letters represent unaltered menu values.

Appendix D contains a list of all possible System Event Codes and their definitions. Appendix E contains a list of all possible User Response Codes and their definitions. See Appendix F for a typical session file.

#### 2.3.6 Peripheral Devices

In addition to stimulus/response data recording, CEDA will also drive peripheral devices (e.g. oculometer, electroencephalograph) which can be used to measure eye movement, brain waves, etc. Each system event will initiate the following sequence of pulses:

Generation of system event - pulse channel 1 (on)  
Presentation of system event for:

graphics display	- pulse channel 2 (on-off)
menu display	- pulse channel 3 (on-off)
table display	- pulse channel 4 (on-off)
user response	- pulse channel 1 (off)

The pulses are internally generated in the PDP11 minicomputer and are transmitted to the peripheral devices via a DEC DRS-11A 48-bit output module. The generation of these pulses is initiated by a CEDA software routine (see High-level Software Design).

## SECTION 3

### OPERATING INSTRUCTIONS

#### 3.1 INTRODUCTION

This section is designed specifically for the operator of CEDA, that is, the mission planner. It is a detailed description of all aspects of user interaction with CEDA. It also discusses how a session is set up and defined and how to set up or eliminate any of the data recording or peripheral devices.

Section 3.2 defines actions necessary to initialize CEDA before the actual execution. Section 3.3 then explains the login procedure step by step: what is visible at the terminals initially, requested entries, and how the computer will respond to the entries. Once logged in, all actions for gathering information or for actually planning missions will be through invocation of the various function keys.

Section 3.4 is on the use of each function. For reference, it is divided by function key. For each key there is a general description of what it allows a user to do, followed by a fairly detailed walk-through of its invocation. Menus, tables, and changes in the graphics display are described, as well as the steps a user must take to use the keys and fill in the menus. This section lists features common to several or all CEDA functions.

#### 3.2 SESSION INITIALIZATION

The disk-resident file INPUT.DAT allows certain session characteristics to be set prior to run-time. It is an unformatted data file which can be "edited" (EDT, EDI, etc.) to change session aids or scenarios.

The layout of INPUT.DAT is list-directed (see FORTRAN Language Manual) format as follows:

<u>Line</u>	<u>Data</u>
1	Data recording units (0 = system clock units 1 = system clock units/1000)

- 2           Number of keys available for session (0 to 17)  
            Number of user stations for this session (1)
- 3           Terminal numbers for each pair (graphics and video)  
            of terminals in the user stations  
            Note: All tasks must be recompiled when terminals  
            (TT numbers) are changed. INSTALL.CMD must also be  
            changed appropriately.
- 4           Key availability for each key on VT100 key pad.  
            They are ordered from top to bottom, left to right.  
            (0 = not available, 1 to 17 = function code  
            corresponds to F# below)

For example the following INPUT.DAT defines a one  
station configuration with TT6 for graphics and  
TT5 for video, data recording units defined by  
the system clock, and 17 function keys available  
as defined.

```
0
17,1
6,5
1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17
```

Notes: Since the current version of CEDA only  
has 12 functions defined, functions  
13-17 default to function 12 (Start/Stop).  
Also function keys can be reorganized  
through the use of INPUT.DAT.  
In order to assure correct user input,  
the caps unlock key must be set on the  
VT100 terminal.

To initiate CEDA, the user should logon to the system as  
privileged and enter the following sequence of commands at the VT100  
terminal console:


```
> @INSTALL
> When prompt appears: @DBFILE
> When prompt appears: @ MISSION
> When prompt appears: cntl Z
> RUN SEXEC
```

Once the user has "stopped" the session, he should enter the next command to clean up the system and purge system files:

@END

The VT100 function key definitions initially delivered with the system are shown in Figure 3-1. (Refer to the file INPUT.DAT). Definitions for the functions are as follows:

- F1 - Graphic Options
- F2 - Data Base Search
- F3 - Identify
- F4 - Full Page Descriptor
- F5 - Grid
- F6 - Zoom 1
- F7 - Zoom 2
- F8 - Zoom 3
- F9 - Airbase Prioritization
- F10 - Interactive Allocator
- F11 - Air Tasking Order
- F12 - Start/Stop



where:

F# - indicates the function key as set by INPUT.DAT.  
 START/STOP - is used to start and stop the session.  
 T# - indicates the paging for tables.  
 ENTER - indicates that the user is finished with the current table (tables).

Figure 3-1. Default Function Key Layout

### 3.3 LOGIN SESSION STARTUP

At the beginning of a CEDA session, the graphics screen will be blank and there will be a form on the VT100 workspace with the following message:

BEGIN SESSION BY PRESSING START/STOP BUTTON.

Press START/STOP button. The button is marked START/STOP and is located to the right of the keyboard. If correctly pressed, a new message will appear on the form requesting the user to fill in his name and rank.

Enter name and rank. Shortly after a map will appear on the graphics screen and the system will be ready for commands.

If the START/STOP button is not pressed when requested, the system will respond:

LOGIN ERROR, PRESS START/STOP BUTTON TO BEGIN.

There are three chances to select the START/STOP button before the system will stop, at which time it must be reinitialized.

### 3.4 FUNCTION KEYS

CEDA uses function keys as its primary method of entering commands. These include obtaining information to help the user plan missions, allocate weapons against targets, confirm missions, and obtain frag orders of confirmed missions. Below, are descriptions of what each function will allow a user to do and the specific instructions on how to use them.

Note: To turn on the graphics cursor for the Identify and Full Page Functions, the button located on the Tektronix 4027 key pad which is marked with the cross hair cursor must be pressed. The arrows which appear on the keypad are then used to move the cursor to the desired position. If the Ramtek monitor is used, the track ball must be rotated until the desired position is reached.

There are several human factors features common to some or all of the CEDA functions described below. They are listed here as a general introduction to this aspect of CEDA.

- Screen - The graphics screen and the video screen will go blank while a new image (map, menu, or table) is being drawn. Once completed, the screen will be turned on again.
- Titles - Menu titles blink when ready to accept user input. A static menu title indicates that the user is locked out, input has been received, and the system is busy processing. Table titles are always static.
- Menu Entry - TAB key moves the cursor forward from one field to the next for user input. BACKSPACE key moves the cursor backward to the previous field to permit user editing of input. RETURN key indicates the user has completed the menu and wishes to enter his input as it exists on the form.
- Menu Errors - If the user enters invalid data into a menu, an error message will appear at the bottom of the video screen.
- Table Paging - For static tables consisting of multiples pages, the user must access different pages through the use of paging keys on the VT100 keypad as described in Section 3.2.
- Table Scrolling - For dynamic tables consisting of multiple pages, the user must use the T1 key to scroll forward and the T2 key to scroll backward.
- Geographic Areas - The user is restricted in the zoom functions to zoom in or out to predefined, non-overlapping areas. These areas are indicated by use of the grid function.

Note that for all of the following functions which are driven by some type of menu input, the user has the option of cancelling the function at any time before hitting the RETURN key. To cancel menu input and the current function, the user must simply press the START/STOP key on the VT100 keypad rather than the RETURN key.

## 1. Graphics Options Menu

### Description:

This menu (see Figure A-1) will allow the user to change the color of targets or airbases on the graphics display terminal or display or remove targets, airbases, SAM rings or allocation pairing lines for missions already planned.

### Simple walk-through:

- Press Function Key #1 to display the Graphics Option Menu. The menu will appear in the workspace with blinking title and the cursor positioned at the first "Y" under the (Y/N) column.

- You can then type an "n" to remove the item from the graphics display or a "y" to display it. "Y" is the default. The tab key will move the cursor to the COLOR column where you may type in any of the following colors:

wht - White	blu - Blue	pur - Purple
red - Red	yel - Yellow	blk - Black
grn - Green	tur - Turquoise	

- You can then continue to tab through, making as many alterations as possible. Note that SAM RINGS and ALLOCATION PAIRING LINES do not have a color but are always displayed in red. When you have made all your changes hit RETURN key.
- The title will stop blinking to indicate the system is processing your request and shortly you will see the changes on the graphics display.
- You may return to the Graphics Option Menu as many times as you like. Each time the initial menu will reflect the changes you made the previous time.



## 2. Data Base Search Menu

### Description:

This menu (see Figure A-2) allows the user to obtain one of two types of information. He may either call up reference tables that give brief data on the members of specified groups of elements, or he may choose from two categories for more complete descriptions of individual members.

The menu presents the categories Friendly Airbases, and Mission Schedule in a column to the left. To the right is a column of available reference tables. The user may only indicate one choice by typing a "y" in the appropriate place: either one category or one item under the reference tables heading. The default for every choice on the Data Base Search Menu is "n".

\* \* \* \* \*

### Simple walk-through:

. When you have pressed Function Key #2, the Data Base Search Menu will appear on your workspace with title blinking and cursor positioned in the first blank under the CATEGORY heading.

. If you want detailed information on any particular element within a category (FRIENDLY AIRBASES, for example) or a reference table (ENEMY ORDER OF BATTLE, for example) push TAB key until the cursor reaches the blank opposite the desired title and type "y" and then press RETURN key.

. After you have pressed RETURN key, the title of the Data Base Search Menu will stop blinking to indicate the system is responding and the menu will be replaced by the desired description.

. If you want more than one category, or table, or some combination of them, you must return to the Data Base Search Menu by pressing Function Key #2 each time.

### 3. Identify

#### Description:

The Identify Function will give terse data on any single target or friendly airbase on the graphics screen. It should be noted that the user identifies a target, adding it to the Identified List, in order to allocate against it.

\* \* \* \* \*

#### Simple walk-through:

- . Move the graphics cursor until it covers the target or airbase that interests you.
- . Press Function Key #3.
- . A brief table (see Figures B-16 and B-17) will appear in the workspace identifying the item. If it is a target, a white numeral will simultaneously show up to its right on the graphics screen, making it a member of the Identified List.
- . If you wish to unidentify a target, repeat the above operation; the target's number will be erased; however; the rest of the identified targets will not be renumbered to account for the space.
- . You may identify up to 99 targets and as many bases as you like.

### 4. Full Page Descriptor

#### Description:

Operating the same way as the Identify Function, the Full Page Descriptor gives more complete information on the object of interest.

\* \* \* \* \*

#### Simple walk-through:

- . Move the graphics cursor to cover the item you wish described.

. Press Function Key #4. You will get a detailed description on the workspace (see Figures B-1 and B-3) of the item you chose. The Full Page Descriptor does not add items to the Identified List.

## 5. Grid

### Description:

The grid is a user visual aid. It superimposes a grid onto the graphics screen to define the individual zoom areas.

\* \* \* \* \*

### Simple walk-through:

. Push Function Key #5.

## 6. Zoom 1

### Description:

The purpose of zoom 1 is to return the map to its original scale after it has been zoomed in.

\* \* \* \* \*

### Simple walk-through:

. Push Function Key #6.

## 7. Zoom 2

### Description:

Zoom 2 zooms the map in by a factor of 2. It will center the quadrant of your choice on the screen and zoom it to full screen size.

\* \* \* \* \*

### Simple walk-through:

. Place the graphics cursor in the desired quadrant. It might be helpful to invoke the grid function first so you can clearly see the quadrant boundaries, but it is not necessary to do so.

. Push Function Key #7.

## 8. Zoom 3

### Description:

This zooms the map in by a factor of 4.

\* \* \* \* \*

### Simple Walk-through:

- . Place the graphics cursor inside the desired area. Again, the grid may be useful.

- . Press Function Key #8.

Note: The invocation of any of the zoom functions will erase the grid.

## 9. Airbase Prioritization

### Description:

There are about one hundred combinations of weapons and airbases that could theoretically be allocated against a given target. But only the first six weapons and first three airbase possibilities actually show up on the workspace. This menu (see Figure A-8) allows the user to set the rules by which the system orders the airbase possibilities.

\* \* \* \* \*

### Simple walk-through:

- . Press Function Key #9 to obtain the Airbase Prioritization Menu. The menu will appear in the workspace with a blinking title and the cursor positioned in the first blank.

- . Indicate your ranking of criteria by typing a numeral between 0 and 9 (0 is for no ranking, 1 is the highest priority) in the blank next to each criterion. The default rules are currently set as 1, 0, 0, 0, 0, 0, 0, 0, 0, 0, respectively (ranked by closest only) and may be used without invoking this function unless a different prioritization scheme is desired. The user ranking however only remains in effect until the end of the next allocation process. At this point they revert to the default values.

- . Tab to subsequent choices and back tab to modify earlier ones until you are satisfied.

- . Then press RETURN key. The title of the menu will stop blinking to indicate that the computer is processing your input.

#### 10. Interactive Allocator

##### Description:

All of the other functions and visual aids in CEDA support the Interactive Allocator. It is at this stage where, based on information gained in the previous sections, the user actually makes a choice of targets to attack and a combination of weapons and airbases to allocate against these targets.

When Function Key #10 is pressed, a menu (see Figure A-3) will appear on the workspace. At the top, under SELECTION CRITERIA FOR TARGETS the user must either specify by number in the Identification List the targets he wishes to attack or type "all" to attack all identified targets.

Under SELECTION CRITERIA FOR RESOURCES the user has the option of typing in the aircraft and ordnance types(s) and friendly airbases to be considered. He may also choose a range of time for time-over-target and either the number of aircraft or probability of damage desired.

Pressing the RETURN key when finished will call a second menu (see Figure A-4) to the workspace. At the top is displayed the identification of one of the targets chosen. This menu allows the user to choose one specific weapon/aircraft combination from among those recommended for allocation against that target. He also has the option to reject the mission entirely at this point. The graphics display also indicates the target being considered by changing its color to white during the allocation process for this target. Once the process is completed, its original color is restored.

If the weapon/aircraft combination chosen is available, then a third menu (see Figure A-5) will come up. At the top of the menu the identification of the target will be displayed, followed by the possible weapon/aircraft combinations, with the user's choice marked. Next the system offers a number of airbases which would be able to supply the weapon/aircraft combination chosen. From these, the user may select one or go back to the Weapon Decision Menu (Figure A-4) and reselect a different weapon/aircraft combination or reject the target altogether.

Finally, if the target is not rejected, a proposed mission will appear (see Figure A-6) and the user may accept the mission, or, if unsatisfied with the probability of damage, or the position of the base with respect to its proposed target, or anything else, may instead reselect another weapon/aircraft combination or base, or reject the mission and target entirely.

The Weapon Decision Menu (Figure A-4) will be redisplayed, with the identification number of the next target requested. The whole procedure will repeat until all of the targets indicated on the original interactive allocation menu are exhausted.

At the end of the allocation process, a Planned Missions Menu (see Figure A-7) will appear on the workspace. Listed will be all of the missions accepted during the allocation process as well as any other planned missions (proposed and confirmed, but not fragged). Here the user may either confirm or reject these missions and may also choose to have the allocation pairing lines removed or displayed on the graphics display terminal. As stated, a maximum of 16 planned missions is possible at any one time.

\* \* \* \* \*

#### Simple walk-through:

. The Allocation Menu is the first one to appear when you push Function Key #9. The menu will appear with a blinking title and the cursor positioned in the first blank. Indicate the targets against which you would like to fly missions by typing in their Identification List numbers: the white numerals that appear to their right on the graphics screen. You can type "all" to allocate against all identified targets.

If you would like to specify resources, advance the cursor by using the TAB key and enter up to four aircraft types (fille, a7d, etc.), no more than one ordnance type (mark82, rocpod, etc.), up to five friendly air-bases (edvv, edab, etc), the time-over-target range (0100, 1400, etc.), and the number of aircraft or probability of damage. For "TOTZ" if the lower limit is omitted, 0100 is assumed and if the upper limit is omitted 2400 is assumed.

- . Press RETURN key when you are satisfied. The title of the menu will stop blinking to signify that the computer is acting on your input.

- . When ready, the Weapon Decision Menu will appear with a blinking title and a list of possible weapon/aircraft combinations. The threats within the target area are also displayed at the bottom of the video terminal. If no weapons can satisfy the selection criteria a message, "NO WEAPON CAN SATISFY PD" will appear at the bottom. The graphics display will show the current target in white.

- . For this target, choose whichever weapon/aircraft combinations you prefer by typing a "y" in the select column.

- . When you are satisfied, press RETURN key. The title will stop blinking.

- . The Airbase Decision Menu will appear with a list of possible airbases which can satisfy the weapons chosen. If no airbase can supply the combination you ordered, you will receive an error message that reads: "NO AIRBASE CAN SATISFY WEAPON CHOICE AND SELECTION CRITERIA". In that case, reselect. It may be that there are insufficient amounts of all of the listed weapons. When this happens, you must reject the target and begin again with less stringent selection criteria.

- . If your choice of weapons can be supplied by one or more airbases, then the Interactive Allocation/Airbase Decision Menu will be displayed with the information already on the workspace. All of the bases listed will be able to satisfy your mission request.

- . Choose one by typing a "y" opposite it in the SELECT column.

- . A suggested mission will then appear. If none of the possible missions satisfy you, then type a "y" into "reject mission and target" at the bottom, in which case you will begin selecting weapons for a second target, or reselect weapons or base for this target, by backtabbing to the appropriate spaces. You must delete your previous choices.

. You also have the option to reselect either the weapon or base at this time.

. If and when you are satisfied with a mission, type "y" in the ACCEPT MISSION space. A new target will be displayed in white on the graphics screen, and you will make weapons and base selections for this target. The process will continue until all of the targets you marked on the original Allocation Menu have either been allocated or rejected.

. At that point, the Planned Missions Menu will come up with blinking title. All of the missions that you have affirmed in this and earlier phases of the Allocation process will appear. For each mission you have the choice to finally confirm or reject, and to remove or display its allocation pairing lines.

. Type "c" for confirm or "r" for reject in the first column opposite each mission and "d" for display or "r" for remove in the second column.

#### 11. Air Tasking Order

##### Description:

The purpose of the Air Tasking Order is to send all confirmed missions to wing command, thereby changing their status from a planned mission to a scheduled mission (fragged). These missions will simultaneously be printed by the line printer and typed on the video screen (see Figure B-18). By generating an ATO, the user reduces the number of planned missions (maximum of 16).

\* \* \* \* \*

##### Simple walk-through:

Once you have completed the Planned Mission Menu and pressed RETURN key, push Function Key #11.

#### 12. Start/Stop

##### Description:

The CEDA session will be initiated and ended by pressing the START/STOP key.

\* \* \* \* \*



**Simple walk-through:**

- . When you are ready to begin, press **START/STOP**.
- . After you have received your last Air Tasking Order, end the session by pressing **START/STOP**.

## SECTION 4

### SAMPLE CEDA SESSION

#### 4.1 INTRODUCTION

This section begins with a discussion of the CEDA problem: what the user is trying to achieve, and how he can best marshal the capability of CEDA to that end. There is also a run-through of a typical session. This will by no means investigate all of the possibilities or complexities of the system, but rather will give the reader a chance to see how each of the functions look as they are used in conjunction with each other and when actual missions are being considered.

#### 4.2 THE TACTICAL SCENARIO

As the user of CEDA, you are trying to plan tomorrow's missions through automated aids as opposed to manual means. Given the scenario for the session (location and definition of the conflict) and the goal (e.g., seek allocations that would quickly achieve air supremacy), the types of missions to be planned that would best accomplish this goal must first be determined.

Once you have decided on your approach, your task is to plan missions by allocating weapon/aircraft combinations from specific airbases against all of the selected targets.

Before actually going into the allocation phase of CEDA it is best to learn as much as possible about the theatre presented to you. There are many tools supplied with CEDA that allow you to do this. The graphics tools, such as the Graphic Options Menu, Grid and Zoom Functions allow you to alter the graphics information displayed on the graphic terminal. In this way, you can narrow the amount of information appearing on the graphics display to focus on specific targets by changing their color, or enlarge a particular area of the map for closer inspection.

There are many tables of information available to you through the Data Base Search Menu that give general information about the friendly airbases, command and control centers, ordnance load codes, aircraft specifications, target types, etc.

In addition, brief or detailed information about a particular target or airbase is available via the Identify and Full-Page Descriptor Functions.

Once you have determined exactly which targets to allocate against and the friendly airbases and their available unit (or squadron) configuration you are ready to begin allocation.

The following section describes a simple typical session which will show the general procedure you should employ when using CEDA.

#### 4.3 THE CEDA SESSION

**Scenario:** Tactical planning in the early stages of a conflict in central European area (current map).

**Goal:** To seek allocations (plan missions) that would quickly achieve air supremacy.

**Method:** Strike enemy airbases and early warning/ground control intercept cites. (EW/GCI).

##### Step 1 Startup System

The scenario and the goal are presented to the user. Since all of the function keys will be available to the user for this session, INPUT.DAT need not be altered. (See section 3.2) After logging on as privileged type the following commands:

```
> @INSTALL
> When prompt appears: @DBFILE
> When prompt appears: @MISION
> When prompt appears: control Z
> RUN SEXEC
```

The user will deduce the approach (method) to accomplish the goal presented by the person running the session and press the "START/STOP" key in response to the message currently present in the workspace. He will respond with name and rank to the next two questions (See Section 3.3, "LOGIN SESSION STARTUP"). The map will be displayed and CEDA is ready for use.

##### Step 2 Invoke Graphic Options Menu to Get Better View of Potential Targets

To better view the potential targets, user invokes Key #1, Graphic Options Menu. To better see the targets, he either assigns enemy order of

battle/electronic a unique color or assigns all other options "blk" (background) and only targets and friendly bases colors.

Step 3 Invoke Identify Function to Determine Which Targets Are Airbases

And EW's

Since the user is only interested in airbases and targets of type EW, he must determine which of the targets on the screen they are. To do this, he must use the Identify Function for each enemy order of battle/electronic target. If it is not an EW or an airbase he can unidentify it by re-identifying it (pressing the Identify Key again). When he has completed this for each target, the ones he is interested in will have a number on the lower right side of the target on the display screen.

Step 4 Invoke Full-Page Descriptor Function to Find Out More Information

about Targets

The user can find out more information about each identified target by using Key #5, the Full-Page Descriptor Key. He can use this to further narrow his choice of targets. (Any undesired targets are simply unidentified by pressing the Identify Key on a previously identified target).

Step 5 Invoke Data Base Search Function

The user now depresses Function Key #2 to invoke the Data Base Search Menu. He then types a "y" in the ELECTRONIC ORDER OF BATTLE category to see that he has, in fact, identified all the desired targets. He then reinvokes the DBS Menu and types a "y" in the IDENTIFIED TARGETS category to recheck his selections. He reinvokes the DBS Menu and types a "y" in the FRIENDLY AIRBASES category to retrieve information on all twelve bases.

Step 6 Invoke Allocation Function/Target Choice

Now that the user has determined several targets to propose strikes against, he invokes the Allocation Function (Function Key #9). He then specifies his

selection criteria for targets by typing the ID #'s in the appropriate spot. He chooses not to make any resource selection.

#### Step 7 Invoke Weapon and Airbase Decision

At this point, the Weapon Decision Table is presented. The user selects a weapon/aircraft combination and waits for airbase information. Next a set of airbases that can supply that weapon/aircraft combination is presented. The user makes his selection. He now has the choice of accepting the mission, rejecting the mission, or reselecting the weapon or base. Assume he has decided to accept the mission.

#### Step 8 Confirm and Display the Missions

After he has invoked steps 6 and 7 for all the desired targets, he will be presented with a table of planned missions. He can then confirm or reject, display or remove all or selected planned missions. He also has the option of doing nothing thereby postponing the decision until later. Assume he confirms.

#### Step 9 Create the Air Tasking Order

At this point he depresses the ATO Key to send the Air Tasking Order to wing commands (hard copy) and has completed the allocation/mission generation process for the selected targets.

At this point, the user may wish to allocate weapons against other sets of targets. To do so, the above steps could be repeated until all targets have missions assigned to them. This example sets up a possible sequence of actions that a user might take, however, each situation presents its own specific problems and CEDDA functions should be invoked in a way that the user finds to be the most natural, straightforward manner. Once the user has solved the problem presented to his satisfaction, the session is ending by pressing the START/STOP Key.

APPENDIX A

MENUS

# GRAPHIC OPTIONS MENU

ENEMY ORDER OF BATTLE	SELECT:	(Y/N)	COLOR
GROUND		Y	YEL
AIR		Y	YEL
ELECTRONIC		Y	YEL
SAW/AA		Y	YEL
NOMINATED TARGETS		Y	RED
IDENTIFIED TARGETS		Y	WHI
FRIENDLY AIRBASES		Y	GRN
COMMAND AND CONTROL		Y	GRN
SAW RINGS		N	
ALLOCATION PAIRING LINES		N	

Figure A-1. Graphic Options Menu (MN01)

# DATA BASE SEARCH MENU

SELECT ONE ONLY			
CATEGORY	SELECT (Y/N)	REFERENCE TABLES	SELECT (Y/N)
FRIENDLY AIRBASES	N	ENEMY ORDER OF BATTLE	
MISSION SCHEDULE	N	GROUND	N
		AIR	N
		ELECTRONIC	N
		SAM/AAA	N
		IDENTIFIED TARGETS	N
		FIGHTER SCHEDULE	N
		ALERT AIRCRAFT	N
		COMMAND AND CONTROL	N
		TARGET TYPE	N
		ORDNANCE LOAD CODES	N
		AIRCRAFT SPECIFICATIONS	N

Figure A-2. Data Base Search Menu (NN02)



# ALLOCATION MENU

## SELECTION CRITERIA FOR TARGETS

IDENTIFIED LIST

(ALL/1,2,...,N)

## SELECTION CRITERIA FOR RESOURCES

AIRCRAFT TYPE(S)

ORIGINANCE TYPE

AIRCRAFT(S)

TOTZ

NUMBER OF AIRCRAFT

OR

PROBABILITY OF DAMAGE

(F4E, A7D, ...)

(6 CHAR)

(1040 NAME)

(7000 TIME)

FROM: 0000 TO: 0000

(2 DIGITS)

(2 DIGITS)

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

---

# INTERACTIVE ALLOCATION/WEAPON DECISION

10 3 1 TARGET NAME PRI TYPE ASX KSM IDIZ CFI LAT/LONG

WEAPON DECISION: FOR THE ABOVE TARGET, CHOOSE ONE OF THE RECOMMENDED WEAPONS.

W-TYPE SOL W-ORD W-DEG INT(SEC) AL(FT) KIAS PD RECH SELECT

- -  
- -  
- -  
- -  
- -  
- -

REJECT TARGET: ■

Figure A-4. Interactive Allocation/Weapon Decision (MN08)

# INTERACTIVE ALLOCATION/AIRBASE DECISION

AIRBASE DECISION: THE FOLLOWING BASES CAN SATISFY MISSION REQUEST

BASE	TARGET	DIST (NM)	NUMBER OF	NUMBER OF	POUNDS	REQD	SELECT ONE
							SELECT

RESELECT WEAPON: REJECT TARGET: REJECT

Figure A-5. Interactive Allocation/Airbase Decision (MN09)

# INTERACTIVE ALLOCATION/MISSION DECISION

ACCEPT MISSION: - RESELECT AIRBASE: - RESELECT WEAPON: - REJECT TARGET: -  
 HSN NSI TDZ TDZ NM/TYP ORD BASE C/S IGI-DEL TYP PD

Figure A-6. Interactive Allocation/Mission Decision (MN9B)

# PLANNED MISSIONS

TO DISPLAY OR REMOVE MISSIONS (ENTER D OR R)  
 TO CONFIRM OR REJECT MISSIONS (ENTER C OR R)

MISSION IDZ TOTZ WTYPE ORD BASE C/S TOT-# TYP PD RF STE D/R C/R




Figure A-7. Planned Missions (MN10)

# AIRBASE PRIORITIZATION CRITERIA

WHEN MORE THAN ONE AIRBASE CAN SATISFY A RESOURCE REQUEST, AIRBASE WILL BE CHOSEN BY THE FOLLOWING CRITERIA.

RANK ORDER BY ENTERING NUMBERS FROM 1 TO 9.

DISTANCE FROM TARGET

CLOSEST

FURTHEST

QUANTITY OF RESOURCE (MAXIMUM)

AIRCRAFT

ORDNANCE

SUPPORT CAPABILITY

EW

UN

WICCAP

AIRBASE CONDITIONS

WEATHER (HIGHEST CEILING)

ACTIVITY (MINIMUM PLANNED MISSIONS)

Figure A-8. Airbase Prioritization (MN11)

APPENDIX B

TABLES

# TARGET DESCRIPTION

NAME  
 ID NUMBER  
 COUNTRY  
 LATEST REPORT:  
 TYPE  
 LOCATION  
 ID NUMBER

DAY MONTH

LAT/LONG /

## INTELLIGENCE RECOMMENDATIONS

W/TYPE 00 DA (00) INTY (00) AL (00) 00  
 2 K035 MARK02 0 10 500 00

## MISSIONS ASSIGNED

NAME NEW T07 T07 W-TYPE 00 BASE SIG CALL T07 T07 T07 T07 T07 T07

REMARKS:

Figure B-1. Target Description (TB01)



# IDENTIFIED TARGET SUMMARY

ID	REF	TARGET-NAME	PRI	TYPE	ASN	NSN	INTZ	CEL	LA/LO/OC

Figure B-2. Identified Target Summary (TB03)

[illegible]

1991  
 1992  
 1993  
 1994  
 1995  
 1996  
 1997  
 1998  
 1999  
 2000  
 2001  
 2002  
 2003  
 2004  
 2005  
 2006  
 2007  
 2008  
 2009  
 2010  
 2011  
 2012  
 2013  
 2014  
 2015  
 2016  
 2017  
 2018  
 2019  
 2020  
 2021  
 2022  
 2023  
 2024  
 2025  
 2026  
 2027  
 2028  
 2029  
 2030

100

**THE  
FEDERAL  
BUREAU  
OF  
INVESTIGATION**

Age Group	Percentage
18-24	100
25-34	90
35-44	80
45-54	70
55-64	60
65-74	50
75-84	40
85+	10

19920930 003500Z 0909

**Figure B-3a. Friendly Airbase Description (TB04)**





MSN	MSN	C/A	NN/TYPE	ORD	ICAO	C/S	ORBIT PI	READ	FR/TO
1120	CAS	A	2/A-10	MARK-82	EDND	PATSY	5255/1141	0	0800/0900
1121	CAS	A	2/A-10	MARK-70	EDAS	POUCH	5104/1107	0	0400/0500
1040	UCA	C	2/F4D	A1M-7E	ELLY	SILLY	5117/1226	15	1400/1700
1060	CAS	A	4/F4E	N-117	EDLS	GLASS	5040/1110	0	1100/1200

Figure B-3c. Friendly Airbase Description (Alert Aircraft)



TYPE	NUM	TYPE	NUM	TYPE	NUM	TYPE	NUM	TYPE	NUM
------	-----	------	-----	------	-----	------	-----	------	-----

Figure B-3d. Friendly Airbase Description (Ordnance)



NUMBER LENGTH WIDTH CONDITION SURFACE ORIENTATION STATE

Figure B-3e. Friendly Airbase Description (Runways)



TYPE    WEIGHT    CAPACITY    RESUPPLY RATE    RESUPPLY WEIGHT

Figure B-3f. Friendly Airbase Description (Petroleum, Oil and Lubricants)

# FRIENDLY AIRBASE SUMMARY

PAGE 1 OF 12

ECUZ

## FRIENDLY AIRBASES - OPERATIONALLY READY AIRCRAFT

UNIT	F117	E3A	C130	KC135
ARMY	25			
F117	25			
W117	2			
PACER		5		
SPIE			10	
STARK			10	

## FRIENDLY AIRBASES - ORDNANCE

MARK2	MARK20
W117	SUP20
CRF52	20M

Figure B-4a. Friendly Airbase Summary (TB05) (Page 1)



# FRIENDLY AIRBASE SUMMARY

PAGE 2 OF 12

EDMB

UNIT	FAO	REFC	F15	C130	F5E
------	-----	------	-----	------	-----

LABEL	15				
LEUP		20			
LUNCH			13		
PAPER	15				
PAVER		12			
SPEND				4	
STAMP	15				
SUPER	15				
ZERA					10

AT000	BLU1	W17	W01	LAD3
-------	------	-----	-----	------

SU1-23	CH024	MARK03	SU142	BLU3
EASTAWK	MARK02	EC0P00	ACW45	ACW700

[illegible]

۱۰۰  
 ۱۰۱  
 ۱۰۲  
 ۱۰۳

[illegible]

AINSB	PLU	HL7	MC	LAU3
SUB23	CU2	MARK3	SUB2	HL3
CASIANK	MARK2	ECPOD	ACU45	AG72

# FRIENDLY AIRBASES SUMMARY PAGE 4 OF 12

EDM

UNIT	F111F	CA	KC135	C130
------	-------	----	-------	------

2440	25			
2015	1			
2442		15		
2401				5

MARK2	CA132	2015
-------	-------	------

2417	MARK20	
2404	SUN20	

# FRIENDLY AIRBASE SUMMARY

PAGE 5 OF 12

EDAR

UNIT	F4C	F4D	C135	F15	KC135
------	-----	-----	------	-----	-------

BLDG	20				
LASER	25				
LINER	20				
LOSER	5				
PATCH	25				
PUNCH	16				
SLEEP	16				
SPARK	10				

ALP23	BLU	ML7	MC1	LAU3
-------	-----	-----	-----	------

SUB23	CM24	MARK83	SUB42	BLU3
CASITANK	MARK82	ECM200	ACM45	ACM718

Figure B-4e. Friendly Airbase Summary (TB05) (Page 5)

DMS

UNIT	A10	C130
------	-----	------

QUANTITY	15
SQUAD	15
TRUCK	2

UNIT	A10	C130
------	-----	------

QUANTITY	15
SQUAD	15
TRUCK	2

Figure B-4f. Friendly Airbase Summary (TB05) (Page 6)

FRIENDLY AIRBASE SUMMARY

END

=====

UNIT	FAC	Q130	F15	RF4C	F4E	VC35
CHAIN	15					
CHIR	4					
CLIF		12				
CONF	15					
HOBY			10			
PARY		13				
PEMY	15					
SL34			10			
VEBO					10	
TIME	15					

=====

SUB23	CH24	MM203	SUB42	ML3
GASTAK	MM202	ECF00	ACM45	ACM70
ML4	ML17	ML1	LAD3	AIM71

Figure B-4g. Friendly Airbase Summary (TB05) (Page 7)

# FRIENDLY AIRBASE SUMMARY PAGE 8 OF 12

EDAW

UNIT	AVG	Q130
------	-----	------

1053	15	
2403	10	
3941	15	

UNIT	AVG	Q130
------	-----	------

0510K	002	WARR3
1403	WARR2	WARR4
2401	W17	20M

2011  
 2012  
 2013  
 2014  
 2015

[illegible][illegible][illegible][illegible]



21 30 341 PAGE 10 OF 12

ARMY ADDRESS SUMMARY

AM3

UNIT C130 A40 F34

CLASS 1

CUR1 15

RES1 2

UNIT C130 A40 F34

CLASS 1

CUR1 15

RES1 2

EWG

UNIT 140 FEB 85C

UNIT	140	FEB	85C
CODE	13		
PLATE	10		
PLATE	20		
SUGG	12		

UNIT 140 FEB 85C

UNIT	140	FEB	85C
CODE	13		
PLATE	10		
PLATE	20		
SUGG	12		

Figure B-4k. Friendly Airbase Summary (TB05) (Page 11)

FRIENDLY AIRBASE SUMMARY

011

UNIT	FAO	KOISS	F15	F5E
------	-----	-------	-----	-----

WAGC	15			
PAWNT		20		
SATIN			13	
SILLY	15			
YAKKY				15

UNIT	FAO	KOISS	F15	F5E
------	-----	-------	-----	-----

AWB3	SUW2	AWB3		
SUW3	AGW5	AGW3		
MC-1	LAU3			

# MISSION SCHEDULE

REF	REF	TOTZ	TOTZ	WVTYPE	ORD	BASE	SIG	CALL	161-DE	TYPE	PD	REF
REF	REF	TOTZ	TOTZ	WVTYPE	ORD	BASE	SIG	CALL	161-DE	TYPE	PD	REF

Figure B-5. Mission Schedule (TB06)

# ENEMY ORDER OF BATTLE GROUND ORDER OF BATTLE

PAGE 1 OF 3

NAME	TYPE	LAT/LONG	UTM	EAT/PR
WITNESS-03	TRK	5255/1141	32P867413	137 0605
WITNESS-6	TRK	5211/1111	32P844590	137 0430
WITNESS-1	TRK	5159/1205	32U195555	137 0430
WITNESS-2	TRK	5133/1152	32P875571	137 0605
WITNESS-3	TRK	5057/1153	32P879167	137 0605
WITNESS-4	TRK	5153/1042	32P869555	137 0605
WITNESS-5	TRK	5159/1112	32P846901	137 0605
WITNESS-6	TRK	5127/1151	32P875103	137 0605
WITNESS-7	TRK	5059/1025	32P865507	137 0605
WITNESS-8	TRK	5039/1105	32P845761	137 0605
WITNESS-9	POL	5313/1118	32P845562	137 0605
WITNESS-10	POL	5209/1132	32U153407	137 0605
WITNESS-11	POL	5049/1135	32P867413	137 0605
WITNESS-12	POL	5120/1130	32P866698	137 0605
WITNESS-13	POL	5203/1207	32U195593	137 0605
WITNESS-14	POL	5145/1350	32U195761	137 0605
WITNESS-15	POL	5204/1250	32U126373	137 0605
WITNESS-16	POL	5159/1230	32U12955	137 0605

Figure B-6a. Enemy Order of Battle-Ground (TB07) (Page 1)

# **ENEMY ORDER OF BATTLE** **GROUND ORDER OF BATTLE**

PAGE 2 OF 3

NAME	TYPE	LAT/LONG	UTM	DATE/HR
ERBERT	NIL	5104/1107	32UP845131	137 0430
SAWFIELD	NIL	5040/1139	32UP469863	137 0430
WALLF-OST	NIL	5127/1208	33UT596299	137 0430
WALLF-WEST	NIL	5128/1153	32UP876459	137 0505
WALLF-EAST	NIL	5128/1201	33UT591462	137 0155
GERA	NIL	5055/1208	33UT593130	137 0615
FURSTENHAUSE	NIL	5227/1403	33UT133805	137 0605
WANDENBURG	NIL	5219/1234	33UT18165	137 0430
WANDENBURG	NIL	5225/1231	33UT16362	137 0505
WUSRELLITZ	NIL	5323/1310	33UT073165	137 0155
WANDENBURG	NIL	5225/1231	33UT16362	137 0615
LEIPZIG	NIL	5117/1226	33UT508439	137 0605
LEIPZIG	IND	5128/1220	33UT504711	137 0430
LEISCHNITTEN	IND	5210/1432	33UT153418	137 0430
DESSAU	IND	5150/1213	33UT100788	137 0505
GOTTOWIS	IND	5143/1415	33UT540904	137 0155
WALLERSTADT	IND	5156/1101	32UPC39340	137 0615
WESSEN	IND	5105/1345	33UT591348	137 0605
KARL MARXSTAD	IND	5048/1252	33UT24038	137 0430

Figure B-6b. Enemy Order of Battle-Ground (TB07) (Page 2)

PAGE 3 OF 3

ENEMY ORDER OF BATTLE  
GROUND ORDER OF BATTLE

NAME	TYPE	LAT/LONG	UTM	DATE/TIME
USARV-590	ARI	5350/1127	328F56575	137 0439
USARV-590	ARI	5213/1143	328F56539	137 0439
USARV-590	ARI	5224/1127	328H14950	137 0439
USARV-590	ARI	5225/1127	328H14956	137 0439
USARV-590	ARI	5224/1102	328H69782	137 0439
USARV-590	ARI	5225/1106	328F36615	137 0605
USARV-590	ARI	5157/1127	328F57328	137 0605
USARV-590	ARI	5226/1129	328H30523	137 0605
USARV-590	ARI	5152/1139	328H10911	137 0605
USARV-590	ARI	5152/1125	328H10262	137 0439
USARV-590	ARI	5050/1059	328F46397	137 0605
USARV-590	ARI	5150/1127	328H10504	137 0605
USARV-590	ARI	5149/1139	328H11204	137 0605
USARV-590	ARI	5112/1055	328F00497	137 0605
USARV-590	ARI	5040/1119	328F49253	137 0439

Figure B-6c. Enemy Order of Battle-Ground (TB07) (Page 3)

# ENEMY ORDER OF BATTLE AIR ORDER OF BATTLE

NAME	TYPE	LA/LONG	W/TYE	ROE	W/TYE
BATHEN	ROC	522/125			137 0615
ALLSTEDT-1	ROC	5132/1050			137 0605
ALLSTEDT-6	ROC	5122/1040			137 0430
PLANEN-1	ROC	5039/1147			137 0505
PLANEN-7	ROC	5028/1223			137 0155
WESSEBORG	FD	5121/1150			137 0505
WAGGARTON	FD	5416/1227			137 0155
WIRUM	FD	5317/1246			137 0615
BRANDENBURG	FD	5227/1227			137 0605
POCHENHOF	FD	5409/1347			137 0430
OWUM	FD	5249/1342			137 0430
WESSEN	FD	5106/1347			137 0430
WAGGARTON	FD	5247/1416			137 0430

Figure B-7. Enemy Order of Battle-Air (TB08)



# ENEMY ORDER OF BATTLE ELECTRONIC ORDER OF BATTLE

NAME	TYPE	LA/LOC	UTM	ME/R
BRANDENBURG	RAD	523/124	33UT18328	137/0430
LEIPZIG	RAD	5114/128	33UT509713	137/0430
STERNAL	RAD	5236/116	33PT60713	137/0430
WAGNERBURG	RAD	5219/114	33PT59990	137/0430
ALLSTEDT	RAD	5226/115	33PT50024	137/0430
STERNAL	EW	5239/119	33PT60000	137/0430
SCHL-S	EW	5031/102	33PT40117	137/0430
FINDE	EW	5277/133	33UT093345	137/0430
BRANDENBURG	EW	5228/125	33UT12394	137/0430
SCHERIN	EW	5345/110	33PT39136	137/0430
WAGNERBURG	EW	5313/111	33PT054559	137/0430
ALLSTEDT	EW	5139/1102	33PT040555	137/0430

Figure B-8. Enemy Order of Battle-Electronic (TB09)

**ENEMY ORDER OF BATTLE**  
SAM/AAA ORDER OF BATTLE

NAME	TYPE	LAT/LONG	UTM	DATE/HR
ZUSSEN	SAM	5211/1340	33UNT90423	13/04/30
PARCHIN-A	SAM	5323/1140	32TFC6546	13/04/30
STERNAL-A	SAM	5235/1140	32TFC63474	13/04/30
WHEWIKEL-A	SAM	5225/1154	32TFC7399	13/04/30
COCHSTED-A	SAM	5154/1125	32TFC5045	13/04/30
KOTHE-B	SAM	5144/1149	32TFC73066	13/04/30
HERSEBURG-A	SAM	5127/1155	32TFC77893	13/04/30
ALLSTEDT-B	SAM	5120/1131	32TFC61397	13/04/30
HERSEBURG-F	SAM	5116/1155	32TFC78317	13/04/30
NIROW-A	SAM	5321/1237	33UNT24360	13/04/30
BRANDENBURG	SAM	5231/1237	33UNT20700	13/04/30
BRANDENBURG	SAM	5223/1238	33UNT21060	13/04/30
JUTERBOG-A	SAM	5158/1252	33UNT28156	13/04/30
FINDW-A	SAM	5254/1340	33UNT91480	13/04/30
GUSTROW-A	AAA	5345/1214	33UNT10073	13/01/55
WITTSTOCK-A	AAA	5319/1220	33UNT12922	13/01/55
WELSTRELITZA	AAA	5325/1305	33UNT99989	13/01/55
WITTENBERGEA	AAA	5258/1262	33UNT98083	13/01/55
KYRITZ-A	AAA	5253/1220	33UNT10061	13/01/55

Figure B-9a. Enemy Order of Battle SAM/AAA (TB10) (Page 1)

**ENEMY ORDER OF BATTLE**  
**SAM/AA ORDER OF BATTLE**

PAGE 2 OF 3

NAME	TYPE	LA/LOS	UT	MT/HR
ALLSTEDT-A	SAM	5128/118	32F352051	137 0505
ZWILSCHEN-A	SAM	5114/1210	33UT97123	137 0155
LEIPZIG-B	SAM	5116/1232	33US12582	137 0155
ERFURT-A	SAM	5107/1108	32F245737	137 0155
ERFURT-B	SAM	5104/1110	32F247234	137 0155
ALTENBURG-A	SAM	5050/1221	33US02464	137 0615
SACHSFELD-A	SAM	5041/1140	32FA70537	137 0605
PLAUE-A	SAM	5027/1219	33UT99744	137 0430
COTTAEIMAGC	SAM	5050/1050	32FA06387	137 0505
BRANTENBURG-A	SAM	5150/1227	33UT10504	137 0155
HALBERSTADT-B	SAM	5148/1230	33UT12504	137 0615
BRANTENBURG-B	SAM	5112/1055	32F208487	137 0605
GROSSCHWITZ	SAM	5040/1110	32FA49253	137 0430
WISNAR-SVD	SAM	5350/1127	32FE50575	137 0430
WAGNERBURG	SAM	5213/1143	32FC55338	137 0430
KYRITZ	SAM	5254/1127	33UT14850	137 0430
POTSCHAM-W	SAM	5225/1252	33UT30696	137 0430
DESMIN	SAM	5354/1302	33UP68782	137 0430
WITTENBERG-B	AAA	5255/1141	32E153413	137 0605

Figure B-9b. Enemy Order of Battle-SAM/AAA (TB10) (Page 2)

ENEMY ORDER OF BATTLE  
SAM/AA ORDER OF BATTLE

NAME	TYPE	LAT/LONG	UIC	DATE
STANDARD-A	AA	5237/1133	32P55635	13/01/55
STANDARD-A	AA	5233/1216	32P556473	13/01/55
STANDARD-A	AA	5230/1140	32P556559	13/01/55
STANDARD-A	AA	5225/1237	32P55657	13/01/55
STANDARD-A	AA	5220/1132	32P556589	13/01/55
STANDARD-A	AA	5212/1229	32P556572	13/01/55
STANDARD-A	AA	5157/1144	32P556519	13/01/55
STANDARD-A	AA	5149/1214	32P556543	13/01/55
STANDARD-A	AA	5131/1219	32P556544	13/01/55
STANDARD-A	AA	5128/1119	32P556551	13/01/55
STANDARD-A	AA	5114/1219	32P5565723	13/01/55
STANDARD-A	AA	5116/1232	32P556592	13/01/55
STANDARD-A	AA	5107/1109	32P5565737	13/01/55
STANDARD-A	AA	5104/1119	32P55657234	13/01/55
STANDARD-A	AA	5059/1221	32P5565264	13/01/55
STANDARD-A	AA	5041/1149	32P55657537	13/01/55
STANDARD-A	AA	5027/1219	32P556574	13/01/55

Figure B-9c. Enemy Order of Battle-SAM/AAA (TB10) (Page 3)

DATE	DESCRIPTION	AMOUNT	CHECK NO.	BANK	INTEREST	TOTAL
1/1/74	STATE OF TEXAS	100.00	100	FEDERAL RESERVE	0.00	100.00
2/1/74	STATE OF TEXAS	100.00	101	FEDERAL RESERVE	0.00	200.00
3/1/74	STATE OF TEXAS	100.00	102	FEDERAL RESERVE	0.00	300.00
4/1/74	STATE OF TEXAS	100.00	103	FEDERAL RESERVE	0.00	400.00
5/1/74	STATE OF TEXAS	100.00	104	FEDERAL RESERVE	0.00	500.00
6/1/74	STATE OF TEXAS	100.00	105	FEDERAL RESERVE	0.00	600.00
7/1/74	STATE OF TEXAS	100.00	106	FEDERAL RESERVE	0.00	700.00
8/1/74	STATE OF TEXAS	100.00	107	FEDERAL RESERVE	0.00	800.00
9/1/74	STATE OF TEXAS	100.00	108	FEDERAL RESERVE	0.00	900.00
10/1/74	STATE OF TEXAS	100.00	109	FEDERAL RESERVE	0.00	1000.00
11/1/74	STATE OF TEXAS	100.00	110	FEDERAL RESERVE	0.00	1100.00
12/1/74	STATE OF TEXAS	100.00	111	FEDERAL RESERVE	0.00	1200.00
1/1/75	STATE OF TEXAS	100.00	112	FEDERAL RESERVE	0.00	1300.00
2/1/75	STATE OF TEXAS	100.00	113	FEDERAL RESERVE	0.00	1400.00
3/1/75	STATE OF TEXAS	100.00	114	FEDERAL RESERVE	0.00	1500.00
4/1/75	STATE OF TEXAS	100.00	115	FEDERAL RESERVE	0.00	1600.00
5/1/75	STATE OF TEXAS	100.00	116	FEDERAL RESERVE	0.00	1700.00
6/1/75	STATE OF TEXAS	100.00	117	FEDERAL RESERVE	0.00	1800.00
7/1/75	STATE OF TEXAS	100.00	118	FEDERAL RESERVE	0.00	1900.00
8/1/75	STATE OF TEXAS	100.00	119	FEDERAL RESERVE	0.00	2000.00
9/1/75	STATE OF TEXAS	100.00	120	FEDERAL RESERVE	0.00	2100.00
10/1/75	STATE OF TEXAS	100.00	121	FEDERAL RESERVE	0.00	2200.00
11/1/75	STATE OF TEXAS	100.00	122	FEDERAL RESERVE	0.00	2300.00
12/1/75	STATE OF TEXAS	100.00	123	FEDERAL RESERVE	0.00	2400.00
1/1/76	STATE OF TEXAS	100.00	124	FEDERAL RESERVE	0.00	2500.00
2/1/76	STATE OF TEXAS	100.00	125	FEDERAL RESERVE	0.00	2600.00
3/1/76	STATE OF TEXAS	100.00	126	FEDERAL RESERVE	0.00	2700.00
4/1/76	STATE OF TEXAS	100.00	127	FEDERAL RESERVE	0.00	2800.00
5/1/76	STATE OF TEXAS	100.00	128	FEDERAL RESERVE	0.00	2900.00
6/1/76	STATE OF TEXAS	100.00	129	FEDERAL RESERVE	0.00	3000.00
7/1/76	STATE OF TEXAS	100.00	130	FEDERAL RESERVE	0.00	3100.00
8/1/76	STATE OF TEXAS	100.00	131	FEDERAL RESERVE	0.00	3200.00
9/1/76	STATE OF TEXAS	100.00	132	FEDERAL RESERVE	0.00	3300.00
10/1/76	STATE OF TEXAS	100.00	133	FEDERAL RESERVE	0.00	3400.00
11/1/76	STATE OF TEXAS	100.00	134	FEDERAL RESERVE	0.00	3500.00
12/1/76	STATE OF TEXAS	100.00	135	FEDERAL RESERVE	0.00	3600.00
1/1/77	STATE OF TEXAS	100.00	136	FEDERAL RESERVE	0.00	3700.00
2/1/77	STATE OF TEXAS	100.00	137	FEDERAL RESERVE	0.00	3800.00
3/1/77	STATE OF TEXAS	100.00	138	FEDERAL RESERVE	0.00	3900.00
4/1/77	STATE OF TEXAS	100.00	139	FEDERAL RESERVE	0.00	4000.00
5/1/77	STATE OF TEXAS	100.00	140	FEDERAL RESERVE	0.00	4100.00
6/1/77	STATE OF TEXAS	100.00	141	FEDERAL RESERVE	0.00	4200.00
7/1/77	STATE OF TEXAS	100.00	142	FEDERAL RESERVE	0.00	4300.00
8/1/77	STATE OF TEXAS	100.00	143	FEDERAL RESERVE	0.00	4400.00
9/1/77	STATE OF TEXAS	100.00	144	FEDERAL RESERVE	0.00	4500.00
10/1/77	STATE OF TEXAS	100.00	145	FEDERAL RESERVE	0.00	4600.00
11/1/77	STATE OF TEXAS	100.00	146	FEDERAL RESERVE	0.00	4700.00
12/1/77	STATE OF TEXAS	100.00	147	FEDERAL RESERVE	0.00	4800.00
1/1/78	STATE OF TEXAS	100.00</				

81

# Alert Aircraft

Serial	Model	W/T	W/T	W/T	W/T	W/T	W/T	W/T	W/T
1129	CAS	A	2/A-19	MARK-02	000	0/0	0/0	0/0	0/0
1121	CAS	A	2/A-19	MARK-70	000	0/0	0/0	0/0	0/0
1049	000	C	2/F-4B	AM-7E	011	0/0	0/0	0/0	0/0
1000	000	A	4/F-4E	H-117	000	0/0	0/0	0/0	0/0

Figure B-11. Alert Aircraft (TB12)

# COMMAND AND CONTROL

NAME	TYPE	C/S	LOCATION	LA/LOC	UTM
JOC		DMCE	KARATE	5132/0418	30C54687
COM 74		BRSS	REARTECHAM	5035/0447	30D86442
5161405	TAC	PST	ROBERT	5002/0530	30E83152
1716	CRG	GLD	JERRYVILLE	4955/0515	30E02391

Figure B-12. Command and Control Centers (TB13)

# TARGET TYPE

TARGET	DESCRIPTION
AA	ANTI-AIR ARTILLERY
AT	ARTILLERY
BR	BRIDGE
EW	EARLY WARNING
IS	INDUSTRIAL SITE
ML	MISC. MILITARY SITE
PO	PETROLEUM OIL, LUBRICANT DEPOT
RA	RADAR
RO	ROCKET
SA	SURFACE-TO-AIR MISSILE SITE
TN	TANK COLUMN
TR	TRUCK COLUMN

Figure B-13 Generic Target Types (TB14)



# ORDNANCE LOAD CODES

PAGE 1 OF 4

NO	ORDNANCE	WEIGHT
001	1 MARK 81 (2000 G)	
002	2 MARK 82 (5000 LB)	
003	12 MARK 82 (5000 LB)	
004	2 MARK 82 (5000 G)	
005	12 MARK 82 (5000 G)	
006	12 H-117 (7500 G)	
007	12 MARK 82 (5000 G) AND 3 H-117 (7500 G)	
008	12 MARK 82 (5000 G) AND 2 MARK 81 (2000 G)	
009	12 MARK 82 (5000 LB) AND 2 MARK 81 (2000 G)	
010	12 MARK 82 (5000 G) AND 12 MARK 82 (5000 LB) AND 3 H-117 (7500 G)	
011	12 GBU 5271	
012	12 MARK 20 (ROCKET)	
013	1 SDB-33, OR HR-106	
014	12 MARK 82 (5000 G) AND 12 MARK 82 (5000 LB) AND 6 MARK 83 (1000 G)	
001	1 ECOPD AND 1 ROCKET POD AND 2 AIM-7E	
002	6 GBU-24 AND 5 H-117 (7500 G) AND 2 AIM-7E	
003	3 GBU-1 (WAPALM) AND 6 H-117 (7500 G) AND 1 ECOPD AND 4 AIM-7E	
004	6 H-117 (7500 G) AND 1 ECOPD AND 5 H-1 AND 2 AIM-7E	
005	11 H-117 (7500 G) AND 1 ECOPD AND 2 AIM-7E	

Figure B-14a. Ordnance Load Codes (TB15) (Page 1)

# ORDNANCE LOAD CODES

PAGE 2 OF 4

SQL	ORDNANCE
B06	5 M-117 (7500 GP) AND 6 MARK 83 (10000 GP) AND 1 ECMPD AND 2 AIM-7E
B07	5 CBU-24 AND 1 ECMPD AND 2 AGM-45 AND 2 AIM-7E
B08	6 CBU-24 AND 1 ECMPD AND 5 HC-1 AND 2 AIM-7E
B09	4 BLU-1 (WPALN) AND 6 MARK-82 AND 4 AIM-7E
B10	3 BLU-1 (WPALN) AND 3 ROCKET PODS AND 4 AIM-7E
B11	3 BLU-1 (WPALN) AND 6 MARK-82 (5000 GP) AND 4 AIM-7E
B12	4 BLU-1 (WPALN) AND 3 ROCKET PODS AND 4 AIM-7E
B13	1 ECMPD AND 2 AGM-45 AND 3 ROCKET PODS AND 2 AIM-7E
B14	6 MARK 82 (5000 HD) AND 3 ROCKET PODS AND 4 AIM-7E
B15	6 MARK 82 (5000 HD) AND 4 AIM-7E
B16	7 BLU-1 (WPALN) AND 4 AIM-7E
B17	12 MARK 82 (5000 GP) AND 2 AIM-7E
B18	4 BLU-1 (WPALN) AND 4 AIM-7E
B19	6 MARK 82 (5000 GP) AND 6 ROCKET PODS AND 4 AIM-7E
B20	1 ECMPD AND 2 AIM-7E
B21	6 MARK 82 (5000 HD) AND 6 ROCKET PODS AND 4 AIM-7E
B22	9 BLU-31B (LAND NINE) AND 1 ECMPD AND 2 AIM-7E
B23	5 CBU-24 AND 1 ECMPD AND 4 AIM-9B AND 2 AIM-7E
B24	4 AIM-7E AND 4 AIM-9B
B25	6 MARK 82 (5000 GP) AND 5 M-117 (7500 GP) AND 1 ECMPD AND 2 AIM-7E

Figure B-14b. Ordnance Load Codes (TB15) (Page 2)

# ORDNANCE LOAD CODES

PAGE 3 OF 4

SL	ORDNANCE
026	5 CBU-24 AND 6 MARK 82 (500 G) AND 1 ECHORD AND 2 AIR-7E
027	5 H-117 (750 G) AND 2 AIR-7E
028	6 CBU-24 AND 1 ECHORD
029	2 ROCKET PODS
030	1 CBU-12
031	2 CBU-12
032	1 ECHORD AND 2 AGM-45 AND 1 CBU-23 CANNON AND 2 AIR-7E
033	1 ECHORD AND 1 AGM-78 AND 1 CBU-23 CANNON AND 2 AIR-7E
001	4 300 GALLON TANK
002	2 BUL-1 (WEPALN) AND 12 MARK 82 (500 G)
003	2 300 GALLON TANK AND 12 MARK 82 (500 G)
004	12 MARK 82 (500 G)
005	6 MARK 84 (200 G)
006	2 300 GALLON TANK AND 10 H-117 (750 G)
007	2 300 GALLON TANK AND 2 CBU-24 AND 12 MARK 82 (500 G)
008	4 CBU-24 AND 2 MARK 84 (200 G)
009	2 300 GALLON TANK AND 4 MARK 84 (200 G)
010	2 300 GALLON TANK AND 2 BUL-1 (WEPALN)
011	6 MARK 83 (1000 G)

Figure B-14c. Ordnance Load Codes (TB15) (Page 3)

ORDNANCE LOAD CODES

SYMBOL	ORDNANCE
012	2 500-24 AND 20 MARK 82 (500 GP)
013	4 BLU-24
014	2 300 GALLON TANK AND 2 BLU-1 (WAPALM)
015	4 BLU-1 (WAPALM)
016	14 H-117 (750 GP)
017	2 300 GALLON TANK AND 4 MARK 84 (2000 GP)
018	20 MARK 82 (500 HP)
019	2 300 GALLON TANK AND 2 BLU-1 (WAPALM) AND 12 MARK 82 (500GP)
020	2 BLU-1 (WAPALM) AND 8 MARK 82 (500 HP)
021	24 MARK 82 (500 GP)
022	2 300 GALLON TANK AND 4 BLU-1 (WAPALM)
001	4 AIM-9B AND 4 AIM-7E AND 940 ROUNDS OF 20MM CANNON
002	2 AIM-9B AND 2 AIM-7E AND 550 ROUNDS OF 20MM CANNON
001	1 ECMP00 AND 2 AGM-45 AND 1 SUU-23 CANNON AND 2 AIM-7E
002	1 ECMP00 AND 1 AGM-78 AND 1 SUU-23 CANNON AND 2 AIM-7E

Figure B-14d. Ordnance Load Codes (TB15) (Page 4)

A/TYPE	ORIGIN	ORIGIN NAME	MIN. SPEED - KIAS	MAX. SPEED - KIAS
F-111	A01	820	540	540
	A02	710	540	540
	A03	760	540	540
	A04	710	540	540
	A05	760	540	540
	A06	740	540	540
	A07	710	540	540
	A08	750	540	540
	A09	750	540	540
	A10	710	540	540
	A11	760	540	540
	A12	800	540	540
	A13	700	540	540
	A14	710	540	540
F-4C,D	B01	450	480	480
	B02	260	480	480
	B03	260	480	480
	B04	300	480	480

# AIRCRAFT CHARACTERISTICS

PAGE 2 OF 5

AC TYPE	ORIGINANCE	COMBAT RADII NM. HI/LOW/HI	MIN. COMBAT SPEED - KTAS
F-4C,D (CONT.)	B04	250	480
	B05	250	480
	B06	350	480
	B07	300	480
	B08	250	480
	B09	400	480
	B10	250	480
	B11	340	480
	B12	380	480
	B13	270	480
	B14	250	480
	B15	340	480
	B16	200	480
	B17	280	480
	B18	290	480
	B19	450	480
	B20	240	480
	B21	300	480
	B22	320	480

Figure B-15b. Aircraft Characteristics (TB16) (Page 2)

# AIRCRAFT CHARACTERISTICS

A/C TYPE	ORIGIN	COMBAT RADIUS NM	HI/LO/HI	MIN. COMBAT SPEED - KTS
F-4D (COMT.)	01	321	400	400
	02	350	400	400
	03	352	400	400
	04	352	400	400
	05	352	400	400
	06	352	400	400
	07	352	400	400
	08	352	400	400
	09	352	400	400
	10	352	400	400
	11	352	400	400
	12	352	400	400
	13	352	400	400
	14	352	400	400
	15	352	400	400
	16	352	400	400
	17	352	400	400
	18	352	400	400
	19	352	400	400
	20	352	400	400
	21	352	400	400
	22	352	400	400
	23	352	400	400
	24	352	400	400
	25	352	400	400
	26	352	400	400
	27	352	400	400
	28	352	400	400
	29	352	400	400
	30	352	400	400
	31	352	400	400
	32	352	400	400
	33	352	400	400
	34	352	400	400
	35	352	400	400
	36	352	400	400
	37	352	400	400
	38	352	400	400
	39	352	400	400
	40	352	400	400
	41	352	400	400
	42	352	400	400
	43	352	400	400
	44	352	400	400
	45	352	400	400
	46	352	400	400
	47	352	400	400
	48	352	400	400
	49	352	400	400
	50	352	400	400
	51	352	400	400
	52	352	400	400
	53	352	400	400
	54	352	400	400
	55	352	400	400
	56	352	400	400
	57	352	400	400
	58	352	400	400
	59	352	400	400
	60	352	400	400

Figure E-15c. Aircraft Characteristics (TE16) (Page 3)

# AIRCRAFT CHARACTERISTICS

A/C TYPE	ORIGIN	COMBAT RADIUS NM. HI/LOW/MI	MIN. COMBAT SPEED - KTAS
A-7, 10 (COMB.)	008	273	450
	009	300	450
	010	330	450
	011	298	450
	012	180	450
	013	270	450
	014	300	450
	015	290	450
	016	180	450
	017	310	450
	018	180	450
	019	280	450
	020	244	450
	021	150	450
	022	300	450
F-5E, F-15	101	1000	450
	102	1000	450

Figure B-15d. Aircraft Characteristics (TB16) (Page 4)



Altitude	Engine	Propeller	Power	Speed	Altitude
10,000	1,000	1,000	1,000	1,000	10,000
8,000	800	800	800	800	8,000
6,000	600	600	600	600	6,000
4,000	400	400	400	400	4,000
2,000	200	200	200	200	2,000
1,000	100	100	100	100	1,000

ID	BE	TARGET NAME	PR	TYPE	ASN	ASN	INTZ	CELL	LA/ONG

Figure B-16. Identify Line - Targets (TB17)

AD-A125 183

CEDA USER'S MANUAL(U) MITRE CORP BEDFORD MA  
J R CALABRO ET AL. JAN 83 MTR-8658 ESD-TR-82-418  
F19628-82-C-0001

2/2

UNCLASSIFIED

F/G 9/2


NL



END

FILMED

DTIC



MICROCOPY RESOLUTION TEST CHART  
NATIONAL BUREAU OF STANDARDS-1963-A

ICAO	NAME	CLASS	DAY/HR	NN/TYPE	NN/TYPE	NN/TYPE	SIA	CELL	LAT/LONG
			/	/	/	/			

Figure B-17. Identify Line-Friendly Airbases (TB18)

# AIR TASKING ORDER

REF	NSN	TDZ	TOTZ	NN/TYPE	ORD	BASE	CALL	SIGN	TGT-BEN	TYPE	PD	RE- FUEL

Figure B-18. Air Tasking Order (TB20)

"CONTINUE SESSION"

Figure B-19. Continue Session (TB21)

**APPENDIX C**

**FUNCTION FLOW**



### Graphic Options Menu




Figure C-1. Function Key #1 - Graphic Options Menu

### Data Base Search Menu




Figure C-2. Function Key #2 - Data Base Search Menu




Figure C-3. Function Key #3 - Identify

# Full Page Descriptor




Figure C-4. Function Key #4 - Full Page Descriptor

Grid

grid  
superimposed  
on  
graphic display

Figure C-5. Function Key #5 - Grid

Zoom 1

graphic display  
map zoomed  
out to original  
scale

Figure C-6. Function Key #6 - Zoom 1




Figure C-7. Function Key #7 - Zoom 2

Zoom 3




Figure C-8. Function Key #8 - Zoom 3



### Airbase Prioritization

MN11
set rules for computer choice in case more than one base satisfies resource request

Figure C-9. Function Key #9 - Airbase Prioritization Menu




Figure C-10. Function Key #10 - Interactive Allocation Menu




Figure C-11. Function Key #11 - Air Tasking Order

Start/Stop

initiates session  
shuts off system  
at the end

Figure C-12. Function Key #12. Start/Stop

**APPENDIX D**

**SYSTEM EVENT CODES**

Possible values for system events are:

Menus: 'MN01' - Graphic Options Menu  
'MN02' - Data Base Search Menu  
'MN07' - Weapons Allocation Menu  
'MN08' - Interactive Allocation/Weapon Decision Menu  
'MN09' - Interactive Allocation/Airbase Decision Menu  
'MN9B' - Interactive Allocation/Mission Decision Menu  
'MN10' - Planned Missions Menu  
'MN11' - Airbase Prioritization Menu

Tables: 'TB01' - Target Description  
'TB03' - Identified Targets Summary  
'TB04' - Friendly Airbase Description  
'TB05' - Friendly Airbases  
'TB06' - Mission Schedule  
'TB07' - Ground Order of Battle  
'TB08' - Air Order of Battle  
'TB09' - Enemy Order of Battle/Electronic  
'TB10' - Enemy Order of Battle/Threat  
'TB11' - Fighter Schedule  
'TB12' - Alert Aircraft  
'TB13' - Command and Control Elements  
'TB14' - Target Type  
'TB15' - Ordnance Load Codes  
'TB16' - Aircraft Characteristics  
'TB17' - Identify Line/Targets  
'TB18' - Identify Line/Friendly Airbase  
'TB20' - Air Tasking Order  
'TB21' - Continue Session

Graphics: 'AR01' - Geographic Area #1 - total area  
'AR02' - Geographic Area #2 - first quadrant  
'AR03' - Geographic Area #3 - second quadrant  
'AR04' - Geographic Area #4 - third quadrant  
'AR05' - Geographic Area #5 - fourth quadrant  
'AR06' - Geographic Area #6 - first quadrant of Area #2  
'AR07' - Geographic Area #7 - second quadrant of Area #2  
'AR08' - Geographic Area #8 - third quadrant of Area 2  
'AR09' - Geographic Area #9 - fourth quadrant of Area #2  
'AR10' - Geographic Area #10 - first quadrant of Area #3  
'AR11' - Geographic Area #11 - second quadrant of Area #3  
'AR12' - Geographic Area #12 - third quadrant of Area #3  
'AR13' - Geographic Area #13 - fourth quadrant of Area #3  
'AR14' - Geographic Area #14 - first quadrant of Area #4  
'AR15' - Geographic Area #15 - second quadrant of Area #4  
'AR16' - Geographic Area #16 - third quadrant of Area #4

'AR17' - Geographic Area #17 - fourth quadrant of Area #4  
'AR18' - Geographic Area #18 - first quadrant of Area #5  
'AR19' - Geographic Area #19 - second quadrant of Area #5  
'AR20' - Geographic Area #20 - third quadrant of Area #5  
'AR21' - Geographic Area #21 - fourth quadrant of Area #5

APPENDIX E

USER RESPONSE CODES



Possible values for user response are:

'F01'	-	Function Key #1
'F02'	-	Function Key #2
'F03'	-	Function Key #3
'F04'	-	Function Key #4
'F05'	-	Function Key #5
'F06'	-	Function Key #6
'F07'	-	Function Key #7
'F08'	-	Function Key #8
'F09'	-	Function Key #9
'F10'	-	Function Key #10
'F11'	-	Function Key #11
'F12'	-	Function Key #12
'F13'	-	Function key #13
'ENTR'	-	Menu entry

The function keys are set prior to session initiation. Refer to the CEDA User's Manual for information on how they are set for the initial system.

APPENDIX F

SAMPLE SESSION DATA

LOGIN	SMITH	PFC		22682
EVENT	AR01	0.363E+02	F 05	0.000E+00
EVENT	AR01	0.972E+01	F 08	0.000E+00
EVENT	AR09	0.269E+02	F 03	0.000E+00
EVENT	TB17	0.405E+01	F 03	0.000E+00
EVENT	TB17	0.117E+01	F 03	0.000E+00
EVENT	TB17	0.262E+02	F 02	0.000E+00
EVENT	MN02	0.332E-01	ENTR	0.945E+01
yNNNNNNNNNNNN				
EVENT	TB05	0.560E+02	F 04	0.000E+00
EVENT	TB01	0.471E+02	F 06	0.000E+00
EVENT	AR01	0.130E+02	F 04	0.000E+00
EVENT	TB04	0.394E+02	F 04	0.000E+00
EVENT	TB04	0.587E+02	F 16	0.000E+00

08:51:38

## GLOSSARY

### Terms

Foreground Information:	Any Target, airbase, or city displayed on the map.
Allocation Pairing Lines:	Line drawn from the friendly airbase that will fly the mission to the target. This is not a flight path.
Confirmed Mission:	A mission that has been explicitly confirmed via Planned Missions menu but not yet sent to wing from the ATO function.
Fragged Mission:	A confirmed mission that has been sent to wing command via ATO function. Also called a scheduled mission.
Menu:	A tabular display accepting user input.
Monitor:	The twenty-fourth line of the VT100 screen on which machine error messages are displayed.
Planned Mission:	The union of all proposed and confirmed missions.
Proposed Mission:	A mission that has been accepted during the last phase of allocation but has not yet been confirmed.
Table:	A tabular display printing information only.
Workspace:	The first 23 lines of VT100 screen on which tabular displays are presented.

### Acronyms & Abbreviations

AAA: anti-aircraft artillery  
A/C: aircraft  
ASN: assignment indicator  
ATO: air tasking order  
AWOP: Automated Weaponneering Optimization Program  
BE: basic encyclopedia  
CAS: close air support  
C/S: call sign  
EOB: enemy order of battle  
EW: electronic warfare  
EW/GCI: early warning/ground control interrupt cite  
G/A: ground or air alert  
ICAO: International Civil Aeronautics Organization - unique airbase code  
KTAS: knots true air speed  
MSN: mission (type if alone)  
NN/TYPE: number of that type of aircraft  
OCA: offensive counter air  
ORD: ordnance  
PD: probability of damage  
POL: petroleum, oil and lubricants  
PRI: priority  
SAM: surface-to-air missiles

SCL: standard configuration load  
STA: status  
TDZ: time of departure (zulu)  
TGT: target  
TOTZ: time over target (zulu)  
UTM: universal transverse mercator - geographic coordinates  
WW: wild weasel